
mdfreader Documentation

Release 2.8

Aymeric Rateau

Nov 06, 2018

CONTENTS

1	mdfreader module documentation	3
1.1	Platform and python version	3
1.2	Dependencies	3
1.3	mdfreader	3
2	mdf module documentation	11
2.1	Dependencies	11
2.2	mdf	11
3	mdf3reader module documentation	17
3.1	mdf3reader	17
4	mdfinfo3 module documentation	23
4.1	Dependencies	23
4.2	mdfinfo3	23
5	mdf4reader module documentation	25
5.1	Dependencies	25
5.2	mdf4reader	25
6	mdfinfo4 module documentation	33
6.1	mdfinfo4	33
7	channel module documentation	41
8	Indices and tables	49
	Python Module Index	51
	Index	53

Contents:

MDFREADER MODULE DOCUMENTATION

Measured Data Format file reader main module

1.1 Platform and python version

With Unix and Windows for python 2.6+ and 3.2+

Author Aymeric Rateau

Created on Sun Oct 10 12:57:28 2010

1.2 Dependencies

- Python >2.6, >3.2 <<http://www.python.org>>
- Numpy >1.6 <<http://numpy.scipy.org>>
- Sympy to convert channels with formula
- bitarray for not byte aligned data parsing
- Matplotlib >1.0 <<http://matplotlib.sourceforge.net>>
- NetCDF
- h5py for the HDF5 export
- xlwt for the excel export (not existing for python3)
- openpyxl for the excel 2007 export
- scipy for the Matlab file conversion
- zlib to uncompress data block if needed

`mdfreader.mdfreader.PythonVersion`

float – Python version currently running, needed for compatibility of both python 2.6+ and 3.2+

1.3 mdfreader

class `mdfreader.mdfreader.Mdf` (*file_name=None, channel_list=None, convert_after_read=True, filter_channel_names=False, no_data_loading=False, compression=False, convert_tables=False, metadata=2*)

Bases: `mdfreader.mdf3reader.Mdf3`, `mdfreader.mdf4reader.Mdf4`

Mdf class

fileName

str – file name

MDFVersionNumber

int – mdf file version number

masterChannelList

dict – Represents data structure: a key per master channel with corresponding value containing a list of channels One key or master channel represents then a data group having same sampling interval.

multiProc

bool – Flag to request channel conversion multi processed for performance improvement. One thread per data group.

fileMetadata

dict – file metadata with minimum keys : author, organisation, project, subject, comment, time, date

read(*file_name = None, multi_processed = False, channel_list=None, convert_after_read*

filter_channel_names=False, no_data_loading=False, compression=False)

reads mdf file version 3.x and 4.x

write (*file_name=None*)

writes simple mdf file

get_channel_data (*channel_name*)

returns channel numpy array

convert_all_channel ()

converts all channel data according to CCBLOCK information

get_channel_unit (*channel_name*)

returns channel unit

plot (*channels*)

Plot channels with Matplotlib

resample (*sampling_time = 0.1, master_channel=None*)

Resamples all data groups

export_to_csv (*file_name = None, sampling = 0.1*)

Exports mdf data into CSV file

export_to_NetCDF (*file_name = None, sampling = None*)

Exports mdf data into netcdf file

export_to_hdf5 (*file_name = None, sampling = None*)

Exports mdf class data structure into hdf5 file

export_to_matlab (*file_name = None*)

Exports mdf class data structure into Matlab file

export_to_excel (*file_name = None*)

Exports mdf data into excel 95 to 2003 file

export_to_xlsx (*file_name=None*)

Exports mdf data into excel 2007 and 2010 file

convert_to_pandas (*sampling=None*)

converts mdf data structure into pandas dataframe(s)

keep_channels (*channel_list*)

keeps only list of channels and removes the other channels

merge_mdf(mdf_class) :
Merges data of 2 mdf classes

Notes

mdf class is a nested dict Channel name is the primary dict key of mdf class At a higher level, each channel includes the following keys :

- 'data' : containing vector of data (numpy)
- 'unit' : unit (string)
- 'master' : master channel of channel (time, crank angle, etc.)
- 'description' : Description of channel
- **'conversion': mdfinfo nested dict for CCBLOCK.** Exist if channel not converted, used to convert with getChannelData method

Examples

```
>>> import mdfreader
>>> yop=mdfreader.Mdf('NameOfFile')
>>> yop.keys() # list channels names
# list channels grouped by raster or master channel
>>> yop.masterChannelList
>>> yop.plot('channelName') or yop.plot({'channel1','channel2'})
>>> yop.resample(0.1) or yop.resample()
>>> yop.export_to_csv(sampling=0.01)
>>> yop.export_to_NetCDF()
>>> yop.export_to_hdf5()
>>> yop.export_to_matlab()
>>> yop.export_to_excel()
>>> yop.export_to_xlsx()
>>> yop.convert_to_pandas() # converts data groups into pandas dataframes
>>> yop.write() # writes mdf file
# drops all the channels except the one in argument
>>> yop.keep_channels({'channel1','channel2','channel3'})
>>> yop.get_channel_data('channelName') # returns channel numpy array
```

convert_all_channels()

Converts all channels from raw data to converted data according to CCBLOCK information Converted data will take more memory.

convert_to_pandas(sampling=None)

converts mdf data structure into pandas dataframe(s)

Parameters **sampling** (float, optional) – resampling interval

Notes

One pandas dataframe is converted per data group Not adapted yet for mdf4 as it considers only time master channels

cut(begin=None, end=None)

Cut data

Parameters

- **begin** (*float*) – beginning value in master channel from which to start cutting in all channels
- **end** (*float*) – ending value in master channel from which to start cutting in all channels

Notes

Use this method if whole data in mdf are using same physical or type of master channel (for instance time).

export_to_NetCDF (*file_name=None, sampling=None*)

Exports mdf data into netcdf file

Parameters

- **file_name** (*str, optional*) – file name. If no name defined, it will use original mdf name and path
- **sampling** (*float, optional*) – sampling interval.

Notes

Dependency: scipy

export_to_csv (*file_name=None, sampling=None*)

Exports mdf data into CSV file

Parameters

- **file_name** (*str, optional*) – file name. If no name defined, it will use original mdf name and path
- **sampling** (*float, optional*) – sampling interval. None by default

Notes

Data saved in CSV file be automatically resampled as it is difficult to save in this format data not sharing same master channel Warning: this can be slow for big data, CSV is text format after all

export_to_excel (*file_name=None*)

Exports mdf data into excel 95 to 2003 file

Parameters **file_name** (*str, optional*) – file name. If no name defined, it will use original mdf name and path

Notes

xlwt is not fast even for small files, consider other binary formats like HDF5 or Matlab If there are more than 256 channels, data will be saved over different worksheets Also Excel 2003 is becoming rare these days, prefer using exportToXlsx Dependencies: xlwt for python 2.6+, xlwt3 for python 3.2+

export_to_hdf5 (*file_name=None, sampling=None, compression=None, compression_opts=None*)

Exports mdf class data structure into hdf5 file

Parameters

- **file_name** (*str, optional*) – file name. If no name defined, it will use original mdf name and path
- **sampling** (*float, optional*) – sampling interval.

- **compression** (*str*, *optional*) – HDF5 compression algorithm. Valid options are ‘gzip’, ‘lzf’. gzip compression recommended for portability. szip compression not supported due to legal reasons.
- **compression_opts** (*int*, *optional*) – HDF5 gzip compression level, 0-9. Only valid if gzip compression is used. Level 4 (default) recommended for best balance between compression and time.

Notes

The maximum attributes will be stored Data structure will be similar has it is in masterChannelList attribute
Dependency: h5py

export_to_matlab (*file_name=None*)

Export mdf data into Matlab file format 5, tentatively compressed

Parameters **file_name** (*str*, *optional*) – file name. If no name defined, it will use original mdf name and path

Notes

This method will dump all data into Matlab file but you will loose below information: - unit and descriptions of channel - data structure, what is corresponding master channel to a channel. Channels might have then different lengths
Dependency: scipy

export_to_xlsx (*file_name=None*)

Exports mdf data into excel 2007 and 2010 file

Parameters **file_name** (*str*, *optional*) – file name. If no name defined, it will use original mdf name and path

Notes

It is recommended to export resampled data for performances
Dependency: openpyxl

get_channel_data (*channel_name*, *raw_data=False*)

Return channel numpy array

Parameters

- **channel_name** (*str*) – channel name
- **raw_data** (*bool*) – flag to return non converted data

Returns converted, if not already done, data corresponding to channel name

Return type numpy array

Notes

This method is the safest to get channel data as numpy array from ‘data’ dict key might contain raw data

keep_channels (*channel_list*)

keeps only list of channels and removes the other channels

Parameters **channel_list** (*list of str*) – list of channel names

merge_mdf (*mdf_class*)

Merges data of 2 mdf classes

Parameters **mdf_class** (*Mdf*) – mdf class instance to be merge with self

Notes

both classes must have been resampled, otherwise, impossible to know master channel to match create union of both channel lists and fill with Nan for unknown sections in channels

plot (*channel_name_list_of_list*)

Plot channels with Matplotlib

Parameters **channel_name_list_of_list** (*str or list of str or list of list of str*) – channel name or list of channel names or list of list of channel names list of list will create multiplots

Notes

Channel description and unit will be tentatively displayed with axis labels

plot_all ()

read (*file_name=None, multi_processed=False, channel_list=None, convert_after_read=True, filter_channel_names=False, no_data_loading=False, compression=False, metadata=2*)
reads mdf file version 3.x and 4.x

Parameters

- **file_name** (*str, optional*) – file name
- **multi_processed** (*bool*) – flag to activate multiprocessing of channel data conversion
- **channel_list** (*list of str, optional*) – list of channel names to be read If you use channelList, reading might be much slower but it will save you memory. Can be used to read big files
- **convert_after_read** (*bool, optional*) – flag to convert channel after read, True by default If you use convertAfterRead by setting it to false, all data from channels will be kept raw, no conversion applied. If many float are stored in file, you can gain from 3 to 4 times memory footprint To calculate value from channel, you can then use method `.getChannelData()`
- **filter_channel_names** (*bool, optional*) – flag to filter long channel names from its module names separated by ‘.’
- **no_data_loading** (*bool, optional*) – Flag to read only file info but no data to have minimum memory use
- **compression** (*bool or str, optional*) – To compress data in memory using `blosc` or `bcolz`, takes cpu time if `compression = int(1 to 9)`, uses `bcolz` for compression if `compression = ‘blosc’`, uses `blosc` for compression Choice given, efficiency depends of data
- **metadata** (*int, optional, default = 2*) – Reading metadata has impact on performance, especially for mdf 4.x using xml. 2: minimal metadata reading (mostly channel blocks) 1: used for `noDataLoading` 0: all metadata reading, including Source Information, Attachment, etc..

Notes

If you keep `convertAfterRead` to true, you can set attribute `mdf.multiProc` to activate channel conversion in multiprocessing. Gain in reading time can be around 30% if file is big and using a lot of float channels

Warning: MultiProc use should be avoided when reading several files in a batch, it is not thread safe. You should better multi process instances of mdf rather than using multiprocessing in mdf class (see implementation of mdfconverter)

resample (*sampling_time=None, master_channel=None*)

Resamples all data groups into one data group having defined sampling interval or sharing same master channel

Parameters

- **sampling_time** (*float, optional*) – resampling interval, None by default. If None, will merge all datagroups into a unique datagroup having the highest sampling rate from all datagroups
- ****or**** –
- **master_channel** (*str, optional*) – master channel name to be used for all channels

Notes

1. resampling is relatively safe for mdf3 as it contains only time series. However, mdf4 can contain also distance, angle, etc. It might make not sense to apply one resampling to several data groups that do not share same kind of master channel (like time resampling to distance or angle data groups) If several kind of data groups are used, you should better use pandas to resample

2. resampling will convert all your channels so be careful for big files and memory consumption

write (*file_name=None, compression=False*)

Writes simple mdf file, same format as originally read, default is 4.x

Parameters

- **file_name** (*str, optional*) – Name of file If file name is not input, written file name will be the one read with appended ‘_new’ string before extension
- **compression** (*bool*) – Flag to store data compressed (from mdf version 4.1) If activated, will write in version 4.1 even if original file is in version 3.x

Notes

All channels will be converted, so size might be bigger than original file

class mdfreader.mdfreader.**MdfInfo**() -> new empty dictionary dict(mapping) -> new dictionary initialized from a mapping object's (key, value) pairs
dict(iterable) -> new dictionary initialized as if via: d = {}
for k, v in iterable: d[k] = v dict(**kwargs) -> new dictionary initialized with the name=value pairs in the keyword argument list. For example: dict(one=1, two=2)

Bases: dict

fid

fileName

filterChannelNames

list_channels (*file_name=None*)

Read MDF file blocks and returns a list of contained channels

Parameters `file_name` (*string*) – file name

Returns `nameList` – list of channel names

Return type list of string

mdfversion

read_info (*file_name=None, fid=None, minimal=0*)

Reads MDF file and extracts its complete structure

Parameters

- **file_name** (*str, optional*) – file name. If not input, uses fileName attribute
- **fid** (*file identifier, optional*) –
- **minimal** (*int*) – 0 will load every metadata 1 will load DG, CG, CN and CC 2 will load only DG

zipfile

MDF MODULE DOCUMENTATION

mdf_skeleton module describing basic mdf structure and methods

Created on Thu Sept 24 2015

Author Aymeric Rateau

2.1 Dependencies

- Python >2.6, >3.2 <<http://www.python.org>>
- Numpy >1.6 <<http://numpy.scipy.org>>

2.2 mdf

class mdfreader.mdf.CompressedData

Bases: object

compression (*a*)

data compression method

Parameters *a* (*numpy array*) – data to be compresses

data

decompression ()

data decompression

Returns

Return type uncompressed numpy array

dtype

class mdfreader.mdf.MdfSkeleton () -> new empty dictionary dict(mapping) -> new dictionary initialized from a mapping object's (key, value) pairs dict(iterable) -> new dictionary initialized as if via: *d* = {} for *k*, *v* in iterable: *d*[*k*] = *v* dict(**kwargs) -> new dictionary initialized with the name=value pairs in the keyword argument list. For example: dict(one=1, two=2)

Bases: dict

MDFVersionNumber

add_channel (*channel_name*, *data*, *master_channel*, *master_type*=1, *unit*="", *description*="", *conversion*=None, *info*=None, *compression*=False, *identifier*=None)
adds channel to mdf dict.

Parameters

- **channel_name** (*str*) – channel name
- **data** (*numpy array*) – numpy array of channel's data
- **master_channel** (*str*) – master channel name
- **master_type** (*int, optional*) – master channel type : 0=None, 1=Time, 2=Angle, 3=Distance, 4=index
- **unit** (*str, optional*) – unit description
- **description** (*str, optional*) – channel description
- **conversion** (*info class, optional*) – conversion description from info class
- **info** (*info class for CNBlock, optional*) – used for CABlock axis creation and channel conversion
- **compression** (*bool*) – flag to ask for channel data compression
- **identifier** (*tuple*) – tuple of int and str following below structure: (data group number, channel group number, channel number), (channel name, channel source, channel path), (group name, group source, group path)

add_metadata (*author=”, organisation=”, project=”, subject=”, comment=”, date=”, time=”*)
adds basic metadata to mdf class

Parameters

- **author** (*str*) – author of file
- **organisation** (*str*) – organisation of author
- **project** (*str*) –
- **subject** (*str*) –
- **comment** (*str*) –
- **date** (*str*) –
- **time** (*str*) –

Notes

All fields are optional, default being empty string

convertAfterRead

convertTables

copy()

copy a mdf class

Returns **mdf_skeleton** – copy of a mdf_skeleton class

Return type class instance

fid

fileMetadata

fileName

filterChannelNames

get_channel (*channel_name*)

Extract channel dict from mdf structure

Parameters **channel_name** (*str*) – channel name

Returns

Return type channel dictionary containing data, description, unit, etc.

get_channel_conversion (*channel_name*)

Extract channel conversion dict from mdf structure

Parameters **channel_name** (*str*) – channel name

Returns

Return type channel conversion dict

get_channel_desc (*channel_name*)

Extract channel description information from mdf structure

Parameters **channel_name** (*str*) – channel name

Returns

Return type channel description string

get_channel_master (*channel_name*)

Extract channel master name from mdf structure

Parameters **channel_name** (*str*) – channel name

Returns

Return type channel master name string

get_channel_master_type (*channel_name*)

Extract channel master type information from mdf structure

Parameters **channel_name** (*str*) – channel name

Returns channel mater type integer

Return type 0=None, 1=Time, 2=Angle, 3=Distance, 4=index

get_channel_unit (*channel_name*)

Returns channel unit string Implemented for a future integration of pint

Parameters **channel_name** (*str*) – channel name

Returns unit string description

Return type str

get_invalid_bit (*channel_name*)

get_invalid_channel (*channel_name*)

info

masterChannelList

multiProc

remove_channel (*channel_name*)

removes channel from mdf dict.

Parameters **channel_name** (*str*) – channel name

Returns

Return type value of mdf dict key=channel_name

remove_channel_conversion (*channel_name*)

removes conversion key from mdf channel dict.

Parameters **channel_name** (*str*) – channel name

Returns

Return type removed value from dict

rename_channel (*channel_name*, *new_name*)

Modifies name of channel

Parameters

- **channel_name** (*str*) – channel name
- **new_name** (*str*) – new channel name

set_channel_attachment (*channel_name*, *attachment*)

Modifies channel attachment

Parameters

- **channel_name** (*str*) – channel name
- **attachment** – channel attachment

set_channel_conversion (*channel_name*, *conversion*)

Modifies conversion dict of channel

Parameters

- **channel_name** (*str*) – channel name
- **conversion** (*dict*) – conversion dictionary

set_channel_data (*channel_name*, *data*, *compression=False*)

Modifies data of channel

Parameters

- **channel_name** (*str*) – channel name
- **data** (*numpy array*) – channel data
- **compression** (*bool or str*) – trigger for data compression

set_channel_desc (*channel_name*, *desc*)

Modifies description of channel

Parameters

- **channel_name** (*str*) – channel name
- **desc** (*str*) – channel description

set_channel_master (*channel_name*, *master*)

Modifies channel master name

Parameters

- **channel_name** (*str*) – channel name
- **master** (*str*) – master channel name

set_channel_master_type (*channel_name*, *master_type*)

Modifies master channel type

Parameters

- **channel_name** (*str*) – channel name
- **master_type** (*int*) – master channel type

set_channel_unit (*channel_name*, *unit*)

Modifies unit of channel

Parameters

- **channel_name** (*str*) – channel name
- **unit** (*str*) – channel unit

set_invalid_bit (*channel_name*, *bit_position*)

returns the invalid bit position of channel

Parameters

- **channel_name** (*str*) – channel name
- **bit_position** – invalid bit position of channel within invalid channel bytes

Returns

Return type bit position

set_invalid_channel (*channel_name*, *invalid_channel*)

zipfile

MDF3READER MODULE DOCUMENTATION

Measured Data Format file reader module for version 3.x

Author Aymeric Rateau

Created on Sun Oct 10 12:57:28 2010

`mdfreader.mdf3reader.PythonVersion`

float – Python version currently running, needed for compatibility of both python 2.6+ and 3.2+

3.1 mdf3reader

class `mdfreader.mdf3reader.DATA` (*fid, pointer*)

Bases: dict

DATA class is organizing record classes itself made of channel. This class inherits from dict. Keys are corresponding to channel group recordID. A DATA class corresponds to a data block, a dict of record classes (one per channel group). Each record class contains a list of channel class representing the structure of channel record.

fid

io.open – file identifier

pointerToData

int – position of Data block in mdf file

BlockLength

int – total size of data block

add_record (*record*)

Adds a new record in DATA class dict

read (*channelSet*)

Reads data block

load_sorted (*record, nameList=None*)

Reads sorted data block from record definition

load_unsorted (*nameList=None*)

Reads unsorted data block, not yet implemented

add_record (*record*)

Adds a new record in DATA class dict

Parameters **record** (*class*) – channel group definition listing record channel classes

load_sorted (*record, name_list=None*)

Reads sorted data block from record definition

Parameters

- **record** (*class*) – channel group definition listing record channel classes
- **name_list** (*set of str, optional*) – list of channel names

Returns

Return type numpy recarray of data

load_unsorted (*name_list=None*)

Reads unsorted data block from record definition

Parameters **name_list** (*set of str, optional*) – list of channel names

Returns

Return type numpy recarray of data

read (*channel_set, file_name*)

Reads data block

Parameters

- **channel_set** (*set of str, optional*) – list of channel names
- **file_name** (*str*) – name of file

```
class mdfreader.mdf3reader.Mdf3 (file_name=None, channel_list=None, con-  
                                vert_after_read=True, filter_channel_names=False,  
                                no_data_loading=False, compression=False, con-  
                                vert_tables=False, metadata=2)
```

Bases: `mdfreader.mdf.MdfSkeleton`

mdf file version 3.0 to 3.3 class

fileName

str – file name

MDFVersionNumber

int – mdf file version number

masterChannelList

dict – Represents data structure: a key per master channel with corresponding value containing a list of channels One key or master channel represents then a data group having same sampling interval.

multiProc

bool – Flag to request channel conversion multi processed for performance improvement. One thread per data group.

convertAfterRead

bool – flag to convert raw data to physical just after read

filterChannelNames

bool – flag to filter long channel names from its module names separated by ‘.’

fileMetadata

dict – file metadata with minimum keys: author, organisation, project, subject, comment, time, date

read3 (*fileName=None, info=None, multiProc=False, channelList=None, convertAfterRead=True*)

Reads mdf 3.x file data and stores it in dict

_get_channel_data3 (*channelName*)

Returns channel numpy array

_convert_channel13 (*channelName*)

converts specific channel from raw to physical data according to CCBLOCK information

_convert_all_channel3()

Converts all channels from raw data to converted data according to CCBlock information

write3 (*fileName=None*)

Writes simple mdf 3.3 file

read3 (*file_name=None, info=None, multi_processed=False, channel_list=None, convert_after_read=True, filter_channel_names=False, compression=False, metadata=2*)

Reads mdf 3.x file data and stores it in dict

Parameters

- **file_name** (*str, optional*) – file name
- **info** (*mdfinfo3.info3 class*) – info3 class containing all MDF Blocks
- **multi_processed** (*bool*) – flag to activate multiprocessing of channel data conversion
- **channel_list** (*list of str, optional*) – list of channel names to be read If you use channelList, reading might be much slower but it will save you memory. Can be used to read big files
- **convert_after_read** (*bool, optional*) – flag to convert channel after read, True by default If you use convertAfterRead by setting it to false, all data from channels will be kept raw, no conversion applied. If many float are stored in file, you can gain from 3 to 4 times memory footprint To calculate value from channel, you can then use method `.get_channel_data()`
- **filter_channel_names** (*bool, optional*) – flag to filter long channel names from its module names separated by ‘.’
- **compression** (*bool, optional*) – flag to activate data compression with blosc
- **metadata** (*int, optional, default = 2*) – Reading metadata has impact on performance, especially for mdf 4.x using xml. 2: minimal metadata reading (mostly channel blocks) 1: used for noDataLoading 0: all metadata reading

write3 (*file_name=None*)

Writes simple mdf 3.3 file

Parameters **file_name** (*str, optional*) – Name of file If file name is not input, written file name will be the one read with appended ‘_new’ string before extension

Notes

All channels will be converted to physical data, so size might be bigger than original file

class mdfreader.mdf3reader.**Record** (*data_group, channel_group*)

Bases: list

record class lists Channel classes, it is representing a channel group

CGrecordLength

int – length of record from channel group block information in Byte

recordLength

int – length of record from channels information in Byte

numberOfRecords

int – number of records in data block

recordID

int – recordID corresponding to channel group

recordIDnumber

int – size of recordID

dataGroup

int: – data group number

channelGroup

int – channel group number

numpyDataRecordFormat

list – list of numpy (dtype) for each channel

dataRecordName

list – list of channel names used for recarray attribute definition

master

dict – define name and number of master channel

recordToChannelMatching

dict – helps to identify nested bits in byte

channelNames

set – channel names to be stored, useful for low memory consumption but slow

hiddenBytes

Bool, False by default – flag in case of non declared channels in record

byte_aligned

Bool, True by default – flag for byte aligned record

addChannel (*info, channelNumber*)**loadInfo** (*info*)**readSortedRecord** (*fid, pointer, channelSet=None*)**readRecordBuf** (*buf, channelSet=None*)**readRecordBits** (*bita, channelSet=None*)**add_channel** (*info, channel_number*)

add a channel in class

Parameters

- **info** (*mdfinfo3.info3 class*) –
- **channel_number** (*int*) – channel number in mdfinfo3.info3 class

load_info (*info*)

gathers records related from info class

Parameters info (*mdfinfo3.info3 class*) –**read_record_bits** (*bit_stream, channel_set=None*)

read stream of record bits by bits in case of not aligned or hidden bytes

Parameters

- **bit_stream** (*stream*) – stream of bytes read in file
- **channel_set** (*Set of str, optional*) – list of channel to read

Returns **rec** – returns dictionary of channel with its corresponding values

Return type dict

read_record_buf (*buf*, *channel_set=None*)

read stream of record bytes

Parameters

- **buf** (*stream*) – stream of bytes read in file
- **channel_set** (*Set of str, optional*) – list of channel to read

Returns **rec** – returns dictionary of channel with its corresponding values

Return type dict

read_sorted_record (*fid*, *pointer*, *channel_set=None*)

reads record, only one channel group per data group

Parameters

- **fid** (*float*) – file identifier
- **pointer** – position in file of data block beginning
- **channel_set** (*Set of str, optional*) – list of channel to read

Returns **rec** – contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Return type numpy recarray

Notes

If channelSet is None, read data using `numpy.core.records.fromfile` that is rather quick. However, in case of large file, you can use channelSet to load only interesting channels or only one channel on demand, but be aware it might be much slower.

MDFINFO3 MODULE DOCUMENTATION

Measured Data Format blocks parser for version 3.x

Created on Thu Dec 9 12:57:28 2014

Author Aymeric Rateau

4.1 Dependencies

- Python >2.6, >3.2 <<http://www.python.org>>
- Numpy >1.6 <<http://numpy.scipy.org>>

`mdfreader.mdfinfo3.PythonVersion`

float – Python version currently running, needed for compatibility of both python 2.6+ and 3.2+

4.2 mdfinfo3

class `mdfreader.mdfinfo3.Info3()` -> new empty dictionary *dict(mapping)* -> new dictionary initialized from a mapping object's (key, value) pairs *dict(iterable)* -> new dictionary initialized as if via: *d = {}* for *k, v* in *iterable*: *d[k] = v* *dict(**kwargs)* -> new dictionary initialized with the *name=value* pairs in the keyword argument list. For example: *dict(one=1, two=2)*

Bases: `dict`

clean_dg_info (*dg*)

delete CN,CC and CG blocks related to data group

Parameters *dg* (*int*) – data group number

fid

fileName

filterChannelNames

list_channels3 (*file_name=None, fid=None*)

reads data, channel group and channel blocks to list channel names

file_name

str – file name

Returns

Return type list of channel names

read_cg_block (*fid*, *dg*, *minimal=0*)
read all CG blocks and relying CN & CC

Parameters

- **fid** (*float*) – file identifier
- **dg** (*int*) – data group number
- **minimal** (*int*) – 0 will load every metadata 1 will load DG, CG, CN and CC 2 will load only DG

read_info3 (*fid*, *minimal=0*)
read all file blocks except data

Parameters

- **fid** (*float*) – file identifier
- **minimal** (*int*) – 0 will load every metadata 1 will load DG, CG, CN and CC 2 will load only DG

`mdfreader.mdinfo3.read_cc_block` (*fid*, *pointer*)
channel conversion block reading

`mdfreader.mdinfo3.read_ce_block` (*fid*, *pointer*)
reads source block

`mdfreader.mdinfo3.read_cg_block` (*fid*, *pointer*)
channel block reading

`mdfreader.mdinfo3.read_cn_block` (*fid*, *pointer*)
channel block reading

`mdfreader.mdinfo3.read_dg_block` (*fid*, *pointer*)
data group block reading

`mdfreader.mdinfo3.read_hd_block` (*fid*, *pointer*, *version=0*)
header block reading

`mdfreader.mdinfo3.read_tx_block` (*fid*, *pointer*)
reads text block

MDF4READER MODULE DOCUMENTATION

Measured Data Format file reader module for version 4.x.

Author Aymeric Rateau

Created on Thu Dec 10 12:57:28 2013

5.1 Dependencies

- Python >2.6, >3.2 <<http://www.python.org>>
- Numpy >1.6 <<http://numpy.scipy.org>>
- bitarray to parse bits in not aligned bytes
- SymPy to convert channels with formula if needed
- zlib to uncompress data block if needed

`mdfreader.mdf4reader.PythonVersion`

float – Python version currently running, needed for compatibility of both python 2.6+ and 3.2+

5.2 mdf4reader

class `mdfreader.mdf4reader.Data()` -> new empty dictionary *dict(mapping)* -> new dictionary initialized from a mapping object's (key, value) pairs *dict(iterable)* -> new dictionary initialized as if via: *d = {}* for *k, v* in *iterable*: *d[k] = v* *dict(**kwargs)* -> new dictionary initialized with the *name=value* pairs in the keyword argument list. For example: *dict(one=1, two=2)*

Bases: `dict`

add_record (*record*)

Adds a new record in Data class dict.

Parameters **record** (*class*) – channel group definition listing record channel classes

fid

load (*record*, *info*, *name_list=None*, *sorted_flag=True*, *vlsd=False*)

Reads data block from record definition

Parameters

- **record** (*class*) – channel group definition listing record channel classes
- **info** (*class*) – contains blocks

- **name_list** (*list of str, optional*) – list of channel names
- **sorted_flag** (*bool, optional*) – flag to know if data block is sorted (only one Channel Group in block) or unsorted (several Channel Groups identified by a recordID). As unsorted block can contain CG records in random order, block is processed iteratively, not in raw like sorted -> much slower reading
- **vlsd** (*bool*) – indicate a sd block, compressed (DZ) or not (SD)

Returns

Return type numpy recarray of data

pointer_to_data

read (*channel_set, info, filename*)

Reads data block

Parameters

- **channel_set** (*set of str*) – set of channel names
- **info** (*info object*) – contains blocks structures
- **filename** – name of file ot read

read_record (*record_id, info, buf*)

read record from a buffer

Parameters

- **record_id** (*int*) – record identifier
- **info** (*class*) – contains blocks
- **buf** (*str*) – buffer of data from file to be converted to channel raw data

type

```
class mdfreader.mdf4reader.Mdf4 (file_name=None,          channel_list=None,          con-  
                                vert_after_read=True,      filter_channel_names=False,  
                                no_data_loading=False,      compression=False,      con-  
                                vert_tables=False, metadata=2)
```

Bases: `mdfreader.mdf.MdfSkeleton`

mdf file reader class from version 4.0 to 4.1.1

fileName

str – file name

MDFVersionNumber

int – mdf file version number

masterChannelList

dict – Represents data structure: a key per master channel with corresponding value containing a list of channels One key or master channel represents then a data group having same sampling interval.

multiProc

bool – Flag to request channel conversion multi processed for performance improvement. One thread per data group.

convertAfterRead

bool – flag to convert raw data to physical just after read

filterChannelNames

bool – flag to filter long channel names from its module names separated by ‘.’

fileMetadata

dict – file metadata with minimum keys : author, organisation, project, subject, comment, time, date

read4 (*fileName=None, info=None, multiProc=False, channelList=None, convertAfterRead=True*)

Reads mdf 4.x file data and stores it in dict

_get_channel_data_4 (*channelName*)

Returns channel numpy array

_convert_channel_data_4 (*channel, channel_name, convert_tables, multiProc=False, Q=None*)

select right conversion and calculates it

_convert_channel_4 (*channelName*)

converts specific channel from raw to physical data according to CCBlock information

_convert_all_channel_4 ()

Converts all channels from raw data to converted data according to CCBlock information

write4 (*file_name=None, compression=False*)

writes mdf 4.1 file

apply_invalid_bit (*channel_name*)

mask data from invalid bit channel if existing

get_channel_name_4 (*name, path*)

returns a list of tuples

apply_invalid_bit (*channel_name*)

Mask data of channel based on its invalid bit definition if there is

Parameters **channel_name** (*str*) – Name of channel

get_channel_name4 (*name, path*)

finds mdf channel name from name and path

Parameters

- **name** (*str*) – channel name
- **path** (*str*) – source path or name, or channel group name, source name or path

Returns

Return type list of tuples (channel_name, (ndg, ncg, ncn))

read4 (*file_name=None, info=None, multi_processed=False, channel_list=None, convert_after_read=True, compression=False, metadata=2*)

Reads mdf 4.x file data and stores it in dict

Parameters

- **file_name** (*str, optional*) – file name
- **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks
- **multi_processed** (*bool*) – flag to activate multiprocessing of channel data conversion
- **channel_list** (*list of str, optional*) – list of channel names to be read If you use channelList, reading might be much slower but it will save you memory. Can be used to read big files
- **convert_after_read** (*bool, optional*) – flag to convert channel after read, True by default If you use convertAfterRead by setting it to false, all data from channels will be kept raw, no conversion applied. If many float are stored in file, you can gain

from 3 to 4 times memory footprint To calculate value from channel, you can then use method `.get_channel_data()`

- **compression** (*bool, optional*) – flag to activate data compression with `blosc`
- **metadata** (*int, optional, default = 2*) – Reading metadata has impact on performance, especially for mdf 4.x using xml. 2: minimal metadata reading (mostly channel blocks) 1: used for `noDataLoading` 0: all metadata reading, including Source Information, Attachment, etc..

write4 (*file_name=None, compression=False*)

Writes simple mdf 4.1 file

Parameters

- **file_name** (*str, optional*) – Name of file If file name is not input, written file name will be the one read with appended ‘_new’ string before extension
- **compression** (*bool*) – flag to store data compressed

Notes

All channels will be converted to physical data, so size might be bigger than original file

class `mdfreader.mdf4reader.Record` (*data_group, channel_group*)

Bases: `list`

CANOpen

CGrecordLength

Flags

MLSD

VLSD

VLSD_CG

add_channel (*info, channel_number*)

add a channel in class

Parameters

- **info** (*mdfinfo4.info4 class*) –
- **channel_number** (*int*) – channel number in `mdfinfo4.info4` class

byte_aligned

channelGroup

channelNames

dataGroup

dataRecordName

generate_chunks ()

calculate data split

Returns

Return type (*n_record_chunk, chunk_size*)

hiddenBytes

initialise_reccarray (*info*, *channel_set*, *n_records*, *dtype=None*, *channels_indexes=None*)

Initialise reccarray

Parameters

- **info** (*info class*) –
- **channel_set** (*set of str, optional*) – set of channel to read
- **n_records** (*int*) – number of records
- **dtype** (*numpy dtype, optional*) –
- **channels_indexes** (*list of int, optional*) –

Returns **rec** – contains a matrix of raw data in a reccarray (attributes corresponding to channel name)

Return type numpy reccarray

invalid_channel

load_info (*info*)

gathers records related from info class

Parameters **info** (*mdfinfo4.info4 class*) –

master

numberOfRecords

numpyDataRecordFormat

read_all_channels_sorted_record (*fid*)

reads all channels from file using numpy fromstring, chunk by chunk

Parameters **fid** – file identifier

Returns **rec** – contains a matrix of raw data in a reccarray (attributes corresponding to channel name)

Return type numpy reccarray

read_channels_from_bytes (*bit_stream*, *info*, *channel_set=None*, *n_records=None*, *dtype=None*, *channels_indexes=None*)

reads stream of record bytes using dataRead module if available otherwise bitarray

Parameters

- **bit_stream** (*stream*) – stream of bytes
- **info** (*info class*) –
- **channel_set** (*set of str, optional*) – set of channel to read
- **n_records** (*int*) – number of records
- **dtype** (*numpy dtype*) –
- **channels_indexes** (*list of int*) –

Returns **rec** – contains a matrix of raw data in a reccarray (attributes corresponding to channel name)

Return type numpy reccarray

read_channels_from_bytes_fallback (*bit_stream*, *info*, *channel_set=None*, *n_records=None*, *dtype=None*, *channels_indexes=None*)

reads stream of record bytes using bitarray in case no dataRead available

Parameters

- **bit_stream** (*stream*) – stream of bytes
- **info** (*info class*) –
- **channel_set** (*set of str, optional*) – set of channel to read
- **n_records** (*int*) – number of records
- **dtype** (*numpy dtype*) –
- **channels_indexes** (*list of int*) –

Returns **rec** – contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Return type numpy recarray

read_not_all_channels_sorted_record (*fid, info, channel_set*)

reads channels from file listed in channelSet

Parameters

- **fid** – file identifier
- **info** (*info class*) –
- **channel_set** (*set of str, optional*) – set of channel to read

Returns **rec** – contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Return type numpy recarray

read_record_buf (*buf, info, channel_set=None*)

read stream of record bytes

Parameters

- **buf** (*stream*) – stream of bytes read in file
- **info** (*class*) – contains blocks structure
- **channel_set** (*set of str, optional*) – set of channel to read

Returns **rec** – returns dictionary of channel with its corresponding values

Return type dict

read_sorted_record (*fid, info, channel_set=None*)

reads record, only one channel group per datagroup

Parameters

- **fid** – file identifier
- **info** – info class
- **channel_set** (*set of str, optional*) – set of channel to read

Returns **rec** – contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Return type numpy recarray

Notes

If channelSet is None, read data using `numpy.core.records.fromfile` that is rather quick. However, in case of large file, you can use channelSet to load only interesting channels or only one channel on demand, but be aware it might be much slower.

recordID

recordIDCFormat

recordIDsize

recordLength

recordToChannelMatching

MDFINFO4 MODULE DOCUMENTATION

Measured Data Format blocks parser for version 4.x

Created on Sun Dec 15 12:57:28 2013

Author Aymeric Rateau

`mdfreader.mdfinfo4.PythonVersion`

float – Python version currently running, needed for compatibility of both python 2.6+ and 3.2+

6.1 mdfinfo4

class `mdfreader.mdfinfo4.ATBlock` (*fid, pointer*)

Bases: dict

reads Attachment block and saves in class dict

class `mdfreader.mdfinfo4.CABlock`

Bases: dict

reads Channel Array block and saves in class dict

load (*byte_offset_base*)

read (*fid, pointer*)

write (*fid*)

class `mdfreader.mdfinfo4.CCBlock`

Bases: dict

reads Channel Conversion block and saves in class dict

read_cc (*fid, pointer*)

class `mdfreader.mdfinfo4.CGBlock` (*fid=None, pointer=None*)

Bases: dict

reads Channel Group block and saves in class dict

read (*fid, pointer*)

write (*fid*)

class `mdfreader.mdfinfo4.CHBlock` (*fid, pointer*)

Bases: dict

reads Channel Hierarchy block and saves in class dict

class mdfreader.mdinfo4.CNBlock

Bases: dict

reads Channel block and saves in class dict

read_cn (***kargs*)

write (*fid*)

class mdfreader.mdinfo4.CommentBlock

Bases: dict

reads or writes Comment block and saves in class dict

load (*data, md_type*)

read_cm_at (*fid, pointer*)

reads Comment block from attachment block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_cc (*fid, pointer*)

reads Comment block from channel conversion block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_cc_unit (*fid, pointer*)

reads Comment block for channel conversion unit

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_cg (*fid, pointer*)

reads Comment block from channel group block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_ch (*fid, pointer*)

reads Comment block from file channel hierarchy block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_cn (*fid, pointer, minimal=True*)

reads Comment block from channel block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

- **minimal** (*boolean*) – flag to reduce metadata parsing

read_cm_cn_unit (*fid, pointer*)

reads Comment block for channel unit

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_dg (*fid, pointer*)

reads Comment block from data group block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_ev (*fid, pointer*)

reads Comment block from event block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_fh (*fid, pointer*)

reads Comment block from file history block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_hd (*fid, pointer*)

reads Comment block from header block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_header (*fid, pointer*)

reads Comment block header

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_si (*fid, pointer*)

reads Comment block from source information block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_tx (*fid, pointer*)

reads TX block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_xml (*fid*)

reads Comment block xml and objectifies it

Parameters **fid** – file identifier

write (*fid*)

class mdfreader.mdinfo4.DGBlock (*fid=None, pointer=None*)

Bases: dict

reads Data Group block and saves in class dict

read (*fid, pointer*)

write (*fid*)

class mdfreader.mdinfo4.DLBlock

Bases: dict

reads Data List block

read (*fid, link_count*)

write (*fid, chunks, position*)

class mdfreader.mdinfo4.DTBlock () -> new empty dictionary dict(mapping) -> new dictionary initialized from a mapping object's (key, value) pairs
dict(iterable) -> new dictionary initialized as if via: d = {}
for k, v in iterable: d[k] = v dict(**kwargs) -> new dictionary
initialized with the name=value pairs in the keyword argument
list. For example: dict(one=1, two=2)

Bases: dict

load (*record_byte_offset, nRecords, pointer*)

write (*fid, data*)

class mdfreader.mdinfo4.DZBlock

Bases: dict

reads Data List block

static decompress_data_block (*block, zip_type, zip_parameter, org_data_length*)
decompress datablock.

Parameters

- **block** (*bytes*) – raw data compressed
- **zip_type** (*int*) – 0 for non transposed, 1 for transposed data
- **zip_parameter** (*int*) – first dimension of matrix to be transposed
- **org_data_length** (*int*) – uncompressed data length

Returns

Return type uncompressed raw data

read (*fid*)

write (*fid, data, record_length*)


```

class mdfreader.mdinfo4.EVBlock (fid, pointer)
    Bases: dict
    reads Event block and saves in class dict

class mdfreader.mdinfo4.FHBlock (fid=None, pointer=None)
    Bases: dict
    reads File History block and save in class dict
    read (fid, pointer)
    write (fid)

class mdfreader.mdinfo4.HDBlock (fid=None)
    Bases: dict
    reads Header block and save in class dict
    read (fid=None)
    write (fid)

class mdfreader.mdinfo4.HLBlock
    Bases: dict
    reads Header List block
    load (record_byte_offset, n_records, position)
    read (fid)
    write (fid, data)

class mdfreader.mdinfo4.IDBlock (fid=None)
    Bases: dict
    reads or writes ID Block
    read (fid)
        reads IDBlock
    static write (fid)
        Writes IDBlock

class mdfreader.mdinfo4.Info4 () -> new empty dictionary dict(mapping) -> new dictionary ini-
    tialized from a mapping object's (key, value) pairs dict(iterable)
    -> new dictionary initialized as if via: d = {} for k, v in iterable:
    d[k] = v dict(**kwargs) -> new dictionary initialized with the
    name=value pairs in the keyword argument list. For example:
    dict(one=1, two=2)

    Bases: dict

    clean_dg_info (dg)
        delete CN,CC and CG blocks related to data group
        Parameters dg (int) – data group number

    fid

    fileName

    list_channels4 (file_name=None, fid=None)
        Read MDF file and extract its complete structure
        Parameters

```

- **file_name** (*str*) – file name
- **fid** –

Returns

Return type list of channel names contained in file

static read_at_block (*fid, pointer*)
reads Attachment blocks

Parameters

- **fid** (*float*) – file identifier
- **pointer** (*int*) – position of ATBlock in file

Returns

Return type Attachments Blocks in a dict

read_cg_block (*fid, dg, channel_name_list=False, minimal=0*)
reads Channel Group blocks

Parameters

- **fid** (*float*) – file identifier
- **dg** (*int*) – data group number
- **channel_name_list** (*bool*) – Flag to reads only channel blocks for listChannels4 method
- **minimal** (*flag*) – to activate minimum content reading for raw data fetching

read_cn_block (*fid, dg, cg, channel_name_list=False, minimal=0*)
reads Channel blocks

Parameters

- **fid** (*float*) – file identifier
- **dg** (*int*) – data group number
- **cg** (*int*) – channel group number in data group
- **channel_name_list** (*bool*) – Flag to reads only channel blocks for listChannels4 method
- **minimal** (*flag*) – to activate minimum content reading for raw data fetching

read_composition (*fid, dg, cg, mlsd_channels*)
check for composition of channels, arrays or structures

Parameters

- **fid** (*float*) – file identifier
- **dg** (*int*) – data group number
- **cg** (*int*) – channel group number in data group
- **mlsd_channels** (*list of int*) – channel numbers

Returns

Return type MLSChannels list of appended Maximum Length Sampling Data channels

read_dg_block (*fid*, *channel_name_list=False*, *minimal=0*)

reads Data Group Blocks

Parameters

- **fid** (*float*) – file identifier
- **channel_name_list** (*bool*) – Flag to reads only channel blocks for listChannels4 method
- **minimal** (*flag*) – to activate minimum content reading for raw data fetching

read_info (*fid*, *minimal*)

read all file blocks except data

Parameters

- **fid** (*float*) – file identifier
- **minimal** (*flag*) – to activate minimum content reading for raw data fetching

static read_sr_block (*fid*, *pointer*)

reads Sample Reduction Blocks

Parameters

- **fid** (*float*) – file identifier
- **pointer** (*int*) – position of SRBlock in file

Returns

Return type Sample Reduction Blocks in a dict

unique_id (*ndg*, *ncg*, *ncn*)

generate unique id tuples

Parameters

- **ndg** (*int*) – data group number
- **ncg** (*int*) – channel group number
- **ncn** (*int*) – channel number

Returns tuples – (channel name, channel source, channel path), (group name, group source, group path)

Return type (data group number, channel group number, channel number),

zipfile

class mdfreader.mdffinfo4.**SIBlock**

Bases: dict

reads Source Information block and saves in class dict

read_si (*fid*, *pointer*)

class mdfreader.mdffinfo4.**SRBlock** (*fid*, *pointer*)

Bases: dict

reads Sample Reduction block and saves in class dict

CHANNEL MODULE DOCUMENTATION

Measured Data Format file reader module.

Author Aymeric Rateau

Created on Wed Oct 04 21:13:28 2017

`mdfreader.channel.PythonVersion`

float – Python version currently running, needed for compatibility of both python 2.6+ and 3.4+

`mdfreader.channel.channel`

class `mdfreader.channel.Channel13` (*info, data_group, channel_group, channel_number, record_id_number*)

Bases: object

Channel class gathers all about channel structure in a record

name

str – Name of channel

unit

str, default empty string – channel unit

desc

str – channel description

conversion

info class – conversion dictionary

channelNumber

int – channel number corresponding to `mdfinfo3.info3` class

signalDataType

int – signal type according to specification

bitCount

int – number of bits used to store channel record

nBytes

int – number of bytes (1 byte = 8 bits) taken by channel record

dataFormat

str – numpy dtype as string

CFormat

struct class instance – struct instance to convert from C Format

byteOffset

int – position of channel record in complete record in bytes

bitOffset

int – bit position of channel value inside byte in case of channel having bit count below 8

recAttributeName

str – channel name compliant to a valid python identifier (recarray attribute)

RecordFormat

list of str – dtype format used for numpy.core.records functions ((name_title,name),str_type)

channelType

int – channel type

posByteBeg

int – start position in number of bit of channel record in complete record

posByteEnd

int – end position in number of bit of channel record in complete record

bit_masking_needed

bool, default false – True if bit masking needed after data read

__init__ (*info, dataGroup, channelGroup, channelNumber, recordIDnumber*)
constructor

__str__ ()
to print class attributes

change_channel_name (*channel_group*)
rename duplicated channel name within unsorted channel groups

change_channel_name (*channel_group*)
In case of duplicate channel names within several channel groups for unsorted data, rename channel name

Parameters **channel_group** (*int*) – channelGroup number

class mdfreader.channel.Channel4

Bases: object

CANOpen_offset ()
CANopen channel bytes offset

Returns

Return type integer, channel bytes offset

VLSD_CG_Flag

attachment (*fid, info*)
In case of sync channel attached to channel

Parameters

- **fid** (*class*) – file identifier
- **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type ATBlock class from mdfinfo4 module

bit_count (*info*)
calculates channel number of bits

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type integer corresponding to channel number of bits

bit_masking_need (*info*)

Valid if bit masking need

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type boolean True if channel needs bit masking, otherwise False

bit_offset (*info*)

channel data bit offset in record

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type integer, channel bit offset

byteOffset

c_format (*info*)

channel data C format

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type string data C format

c_format_structure (*info*)

channel data C format struct object

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type string data C format struct object

ca_block (*info*)

Extracts channel CA Block from info4

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type CABlock object from mdfinfo4 module

calc_byte_offset (*info*)

channel data bytes offset in record (without record id)

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type integer, channel bytes offset

calc_bytes (*info*)

calculates channel bytes number

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type number of bytes integer

change_channel_name (*channel_group*)

In case of duplicate channel names within several channel groups for unsorted data, rename channel name

Parameters **channel_group** (*int*) – channelGroup number

channelGroup

channelNumber

channel_sync_type (*info*)

Extracts channel sync type from info4

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

- *integer corresponding to channel sync type*
- *0 no sync, normal data*
- *1 time*
- *2 angle*
- *3 distance*
- *4 index*

channel_type (*info*)

Extracts channel type from info4

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

- *integer describing channel type*
- *0 normal channel*
- *1 variable length*
- *2 master channel*
- *3 virtual master channel*
- *4 sync channel*
- *5 max length data*
- *6 virtual data channel*

cn_block (*info*)

channel block

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type CNBlock class from mdfinfo4 module

conversion (*info*)

channel conversion CCBlock

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type *CCBlock*

data (*info*)
returns data block pointer for VLSD, MLD or sync channels

dataGroup

data_format (*info*)
channel numpy.core.records data format

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type string data format

desc (*info*)
channel description

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type channel description string

has_invalid_bit (*info*)

invalid_bit (*info*)
extracts from info4 the channels valid bits positions

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type channel valid bit position

is_ca_block (*info*)

isnumeric (*info*)
check this is numeric channel from data type

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type boolean, true if numeric channel, otherwise false

little_endian (*info*)
check if channel is little endian

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type boolean

nBytes

name

native_data_format (*info*)

numpy_format (*info*)
channel numpy.core.records data format

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns **endian, dataType**

Return type string data format

pos_bit_beg (*info*)

channel data bit starting position in record

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type integer, channel bit starting position

pos_bit_end (*info*)

channel data bit ending position in record

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type integer, channel bit ending position

pos_byte_beg (*info*)

channel data bytes starting position in record

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type integer, channel bytes starting position

pos_byte_end (*info*)

channel data bytes ending position in record

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type integer, channel bytes ending position

record_attribute_name ()

clean up channel name from unauthorised characters

Returns

Return type channel name compliant to python attributes names (for recarray)

record_id_size (*info*)

Extracts record id size from info4

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

- *integer describing record id size*
- *0 no record id used*
- *1 uint8*
- *2 uint16*
- *4 uint32*
- *8 uint64*

set (*info, data_group, channel_group, channel_number*)

channel initialisation

Parameters

- **info** (*mdfinfo4.info4 class*) –

- **data_group** (*int*) – data group number in mdinfo4.info4 class
- **channel_group** (*int*) – channel group number in mdinfo4.info4 class
- **channel_number** (*int*) – channel number in mdinfo4.info4 class

set_CANOpen (*info, data_group, channel_group, channel_number, name*)

CANOpen channel initialisation

Parameters

- **info** (*mdinfo4.info4 class*) –
- **data_group** (*int*) – data group number in mdinfo4.info4 class
- **channel_group** (*int*) – channel group number in mdinfo4.info4 class
- **channel_number** (*int*) – channel number in mdinfo4.info4 class
- **name** (*str*) – name of channel. Should be in ('ms', 'day', 'days', 'hour', 'month', 'minute', 'year')

set_invalid_bytes (*info, data_group, channel_group, channel_number*)

invalid_bytes channel initialisation

Parameters

- **info** (*mdinfo4.info4 class*) –
- **data_group** (*int*) – data group number in mdinfo4.info4 class
- **channel_group** (*int*) – channel group number in mdinfo4.info4 class
- **channel_number** (*int*) – channel number in mdinfo4.info4 class

signal_data_type (*info, byte_aligned=True*)

extract signal data type from info4 class

Parameters

- **info** (*mdinfo4.info4 class*) – info4 class containing all MDF Blocks
- **byte_aligned** (*bool*) – flag activated if channel is part of a record byte aligned

Returns

- *integer corresponding to channel data type*
- *0 unsigned integer little endian*
- *1 unsigned integer big endian*
- *2 signed integer little endian*
- *3 signed integer big endian*
- *4 float little endian*
- *5 float big endian*
- *6 string latin*
- *7 string utf-8*
- *9 string utf-16*
- *10 byte array*
- *11 mime sample*

- 12 *mime stream*
- 13 *CANopen date*
- 14 *CANopen time*

type

unit (*info*)

channel unit

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type channel unit string

`mdfreader.channel.array_format4` (*signal_data_type, number_of_bytes*)

function returning numpy style string from channel data type and number of bits

Parameters

- **signal_data_type** (*int*) – channel data type according to specification
- **number_of_bytes** (*int*) – number of bytes taken by channel data in a record

Returns **endian, data_type** – numpy dtype format used by `numpy.core.records` to read channel raw data

Return type str

`mdfreader.channel.data_type_format4` (*signal_data_type, number_of_bytes*)

function returning C format string from channel data type and number of bits

Parameters

- **signal_data_type** (*int*) – channel data type according to specification
- **number_of_bytes** (*int*) – number of bytes taken by channel data in a record

Returns **data_type** – C format used by `fread` to read channel raw data

Return type str

INDICES AND TABLES

- `genindex`
- `modindex`
- `search`

PYTHON MODULE INDEX

m

- `mdfreader.channel`, 41
- `mdfreader.mdf`, 11
- `mdfreader.mdf3reader`, 17
- `mdfreader.mdf4reader`, 25
- `mdfreader.mdffinfo3`, 23
- `mdfreader.mdffinfo4`, 33
- `mdfreader.mdfreader`, 3

Symbols

__init__() (mdfreader.channel.Channel3 method), 42
 __str__() (mdfreader.channel.Channel3 method), 42
 _convert_all_channel3() (mdfreader.mdf3reader.Mdf3 method), 18
 _convert_all_channel_4() (mdfreader.mdf4reader.Mdf4 method), 27
 _convert_channel3() (mdfreader.mdf3reader.Mdf3 method), 18
 _convert_channel_4() (mdfreader.mdf4reader.Mdf4 method), 27
 _convert_channel_data_4() (mdfreader.mdf4reader.Mdf4 method), 27
 _get_channel_data3() (mdfreader.mdf3reader.Mdf3 method), 18
 _get_channel_data_4() (mdfreader.mdf4reader.Mdf4 method), 27

A

add_channel() (mdfreader.mdf.MdfSkeleton method), 11
 add_channel() (mdfreader.mdf3reader.Record method), 20
 add_channel() (mdfreader.mdf4reader.Record method), 28
 add_metadata() (mdfreader.mdf.MdfSkeleton method), 12
 add_record() (mdfreader.mdf3reader.DATA method), 17
 add_record() (mdfreader.mdf4reader.Data method), 25
 addChannel() (mdfreader.mdf3reader.Record method), 20
 apply_invalid_bit() (mdfreader.mdf4reader.Mdf4 method), 27
 array_format4() (in module mdfreader.channel), 48
 ATBlock (class in mdfreader.mdinfo4), 33
 attachment() (mdfreader.channel.Channel4 method), 42

B

bit_count() (mdfreader.channel.Channel4 method), 42
 bit_masking_need() (mdfreader.channel.Channel4 method), 43
 bit_masking_needed (mdfreader.channel.Channel3 attribute), 42
 bit_offset() (mdfreader.channel.Channel4 method), 43

bitCount (mdfreader.channel.Channel3 attribute), 41
 bitOffset (mdfreader.channel.Channel3 attribute), 42
 BlockLength (mdfreader.mdf3reader.DATA attribute), 17
 byte_aligned (mdfreader.mdf3reader.Record attribute), 20
 byte_aligned (mdfreader.mdf4reader.Record attribute), 28
 byteOffset (mdfreader.channel.Channel3 attribute), 41
 byteOffset (mdfreader.channel.Channel4 attribute), 43

C

c_format() (mdfreader.channel.Channel4 method), 43
 c_format_structure() (mdfreader.channel.Channel4 method), 43
 ca_block() (mdfreader.channel.Channel4 method), 43
 CABlock (class in mdfreader.mdinfo4), 33
 calc_byte_offset() (mdfreader.channel.Channel4 method), 43
 calc_bytes() (mdfreader.channel.Channel4 method), 43
 CANOpen (mdfreader.mdf4reader.Record attribute), 28
 CANOpen_offset() (mdfreader.channel.Channel4 method), 42
 CCBlock (class in mdfreader.mdinfo4), 33
 CFormat (mdfreader.channel.Channel3 attribute), 41
 CGBlock (class in mdfreader.mdinfo4), 33
 CGrecordLength (mdfreader.mdf3reader.Record attribute), 19
 CGrecordLength (mdfreader.mdf4reader.Record attribute), 28
 change_channel_name() (mdfreader.channel.Channel3 method), 42
 change_channel_name() (mdfreader.channel.Channel4 method), 44
 channel (in module mdfreader.channel), 41
 Channel3 (class in mdfreader.channel), 41
 Channel4 (class in mdfreader.channel), 42
 channel_sync_type() (mdfreader.channel.Channel4 method), 44
 channel_type() (mdfreader.channel.Channel4 method), 44
 channelGroup (mdfreader.channel.Channel4 attribute), 44
 channelGroup (mdfreader.mdf3reader.Record attribute), 20

- channelGroup (mdfreader.mdf4reader.Record attribute), 28
 - channelNames (mdfreader.mdf3reader.Record attribute), 20
 - channelNames (mdfreader.mdf4reader.Record attribute), 28
 - channelNumber (mdfreader.channel.Channel3 attribute), 41
 - channelNumber (mdfreader.channel.Channel4 attribute), 44
 - channelType (mdfreader.channel.Channel3 attribute), 42
 - CHBlock (class in mdfreader.mdfinfo4), 33
 - clean_dg_info() (mdfreader.mdfinfo3.Info3 method), 23
 - clean_dg_info() (mdfreader.mdfinfo4.Info4 method), 37
 - cn_block() (mdfreader.channel.Channel4 method), 44
 - CNBlock (class in mdfreader.mdfinfo4), 33
 - CommentBlock (class in mdfreader.mdfinfo4), 34
 - CompressedData (class in mdfreader.mdf), 11
 - compression() (mdfreader.mdf.CompressedData method), 11
 - conversion (mdfreader.channel.Channel3 attribute), 41
 - conversion() (mdfreader.channel.Channel4 method), 44
 - convert_all_channel() (mdfreader.mdfreader.Mdf method), 4
 - convert_all_channels() (mdfreader.mdfreader.Mdf method), 5
 - convert_to_pandas() (mdfreader.mdfreader.Mdf method), 4, 5
 - convertAfterRead (mdfreader.mdf.MdfSkeleton attribute), 12
 - convertAfterRead (mdfreader.mdf3reader.Mdf3 attribute), 18
 - convertAfterRead (mdfreader.mdf4reader.Mdf4 attribute), 26
 - convertTables (mdfreader.mdf.MdfSkeleton attribute), 12
 - copy() (mdfreader.mdf.MdfSkeleton method), 12
 - cut() (mdfreader.mdfreader.Mdf method), 5
- ## D
- DATA (class in mdfreader.mdf3reader), 17
 - Data (class in mdfreader.mdf4reader), 25
 - data (mdfreader.mdf.CompressedData attribute), 11
 - data() (mdfreader.channel.Channel4 method), 44
 - data_format() (mdfreader.channel.Channel4 method), 45
 - data_type_format4() (in module mdfreader.channel), 48
 - dataFormat (mdfreader.channel.Channel3 attribute), 41
 - dataGroup (mdfreader.channel.Channel4 attribute), 45
 - dataGroup (mdfreader.mdf3reader.Record attribute), 20
 - dataGroup (mdfreader.mdf4reader.Record attribute), 28
 - dataRecordName (mdfreader.mdf3reader.Record attribute), 20
 - dataRecordName (mdfreader.mdf4reader.Record attribute), 28
 - decompress_data_block() (mdfreader.mdfinfo4.DZBlock static method), 36
 - decompression() (mdfreader.mdf.CompressedData method), 11
 - desc (mdfreader.channel.Channel3 attribute), 41
 - desc() (mdfreader.channel.Channel4 method), 45
 - DGBlock (class in mdfreader.mdfinfo4), 36
 - DLBlock (class in mdfreader.mdfinfo4), 36
 - DTBlock (class in mdfreader.mdfinfo4), 36
 - dtype (mdfreader.mdf.CompressedData attribute), 11
 - DZBlock (class in mdfreader.mdfinfo4), 36
- ## E
- EVBlock (class in mdfreader.mdfinfo4), 36
 - export_to_csv() (mdfreader.mdfreader.Mdf method), 4, 6
 - export_to_excel() (mdfreader.mdfreader.Mdf method), 4, 6
 - export_to_hdf5() (mdfreader.mdfreader.Mdf method), 4, 6
 - export_to_matlab() (mdfreader.mdfreader.Mdf method), 4, 7
 - export_to_NetCDF() (mdfreader.mdfreader.Mdf method), 4, 6
 - export_to_xlsx() (mdfreader.mdfreader.Mdf method), 4, 7
- ## F
- FHBlock (class in mdfreader.mdfinfo4), 37
 - fid (mdfreader.mdf.MdfSkeleton attribute), 12
 - fid (mdfreader.mdf3reader.DATA attribute), 17
 - fid (mdfreader.mdf4reader.Data attribute), 25
 - fid (mdfreader.mdfinfo3.Info3 attribute), 23
 - fid (mdfreader.mdfinfo4.Info4 attribute), 37
 - fid (mdfreader.mdfreader.MdfInfo attribute), 9
 - file_name (mdfreader.mdfinfo3.Info3 attribute), 23
 - fileMetadata (mdfreader.mdf.MdfSkeleton attribute), 12
 - fileMetadata (mdfreader.mdf3reader.Mdf3 attribute), 18
 - fileMetadata (mdfreader.mdf4reader.Mdf4 attribute), 26
 - fileMetadata (mdfreader.mdfreader.Mdf attribute), 4
 - fileName (mdfreader.mdf.MdfSkeleton attribute), 12
 - fileName (mdfreader.mdf3reader.Mdf3 attribute), 18
 - fileName (mdfreader.mdf4reader.Mdf4 attribute), 26
 - fileName (mdfreader.mdfinfo3.Info3 attribute), 23
 - fileName (mdfreader.mdfinfo4.Info4 attribute), 37
 - fileName (mdfreader.mdfreader.Mdf attribute), 3
 - fileName (mdfreader.mdfreader.MdfInfo attribute), 9
 - filterChannelNames (mdfreader.mdf.MdfSkeleton attribute), 12
 - filterChannelNames (mdfreader.mdf3reader.Mdf3 attribute), 18
 - filterChannelNames (mdfreader.mdf4reader.Mdf4 attribute), 26
 - filterChannelNames (mdfreader.mdfinfo3.Info3 attribute), 23

`filterChannelNames` (mdfreader.mdfreader.MdfInfo attribute), 9

`Flags` (mdfreader.mdf4reader.Record attribute), 28

G

`generate_chunks()` (mdfreader.mdf4reader.Record method), 28

`get_channel()` (mdfreader.mdf.MdfSkeleton method), 12

`get_channel_conversion()` (mdfreader.mdf.MdfSkeleton method), 13

`get_channel_data()` (mdfreader.mdfreader.Mdf method), 4, 7

`get_channel_desc()` (mdfreader.mdf.MdfSkeleton method), 13

`get_channel_master()` (mdfreader.mdf.MdfSkeleton method), 13

`get_channel_master_type()` (mdfreader.mdf.MdfSkeleton method), 13

`get_channel_name4()` (mdfreader.mdf4reader.Mdf4 method), 27

`get_channel_name_4()` (mdfreader.mdf4reader.Mdf4 method), 27

`get_channel_unit()` (mdfreader.mdf.MdfSkeleton method), 13

`get_channel_unit()` (mdfreader.mdfreader.Mdf method), 4

`get_invalid_bit()` (mdfreader.mdf.MdfSkeleton method), 13

`get_invalid_channel()` (mdfreader.mdf.MdfSkeleton method), 13

H

`has_invalid_bit()` (mdfreader.channel.Channel4 method), 45

`HDBlock` (class in mdfreader.mdfinfo4), 37

`hiddenBytes` (mdfreader.mdf3reader.Record attribute), 20

`hiddenBytes` (mdfreader.mdf4reader.Record attribute), 28

`HLBlock` (class in mdfreader.mdfinfo4), 37

I

`IDBlock` (class in mdfreader.mdfinfo4), 37

`info` (mdfreader.mdf.MdfSkeleton attribute), 13

`Info3` (class in mdfreader.mdfinfo3), 23

`Info4` (class in mdfreader.mdfinfo4), 37

`initialise_rearray()` (mdfreader.mdf4reader.Record method), 28

`invalid_bit()` (mdfreader.channel.Channel4 method), 45

`invalid_channel` (mdfreader.mdf4reader.Record attribute), 29

`is_ca_block()` (mdfreader.channel.Channel4 method), 45

`isnumeric()` (mdfreader.channel.Channel4 method), 45

K

`keep_channels()` (mdfreader.mdfreader.Mdf method), 4, 7

L

`list_channels()` (mdfreader.mdfreader.MdfInfo method), 9

`list_channels3()` (mdfreader.mdfinfo3.Info3 method), 23

`list_channels4()` (mdfreader.mdfinfo4.Info4 method), 37

`little_endian()` (mdfreader.channel.Channel4 method), 45

`load()` (mdfreader.mdf4reader.Data method), 25

`load()` (mdfreader.mdfinfo4.CABlock method), 33

`load()` (mdfreader.mdfinfo4.CommentBlock method), 34

`load()` (mdfreader.mdfinfo4.DTBlock method), 36

`load()` (mdfreader.mdfinfo4.HLBlock method), 37

`load_info()` (mdfreader.mdf3reader.Record method), 20

`load_info()` (mdfreader.mdf4reader.Record method), 29

`load_sorted()` (mdfreader.mdf3reader.DATA method), 17

`load_unsorted()` (mdfreader.mdf3reader.DATA method), 17, 18

`loadInfo()` (mdfreader.mdf3reader.Record method), 20

M

`master` (mdfreader.mdf3reader.Record attribute), 20

`master` (mdfreader.mdf4reader.Record attribute), 29

`masterChannelList` (mdfreader.mdf.MdfSkeleton attribute), 13

`masterChannelList` (mdfreader.mdf3reader.Mdf3 attribute), 18

`masterChannelList` (mdfreader.mdf4reader.Mdf4 attribute), 26

`masterChannelList` (mdfreader.mdfreader.Mdf attribute), 4

`Mdf` (class in mdfreader.mdfreader), 3

`Mdf3` (class in mdfreader.mdf3reader), 18

`Mdf4` (class in mdfreader.mdf4reader), 26

`MdfInfo` (class in mdfreader.mdfreader), 9

`mdfreader.channel` (module), 41

`mdfreader.mdf` (module), 11

`mdfreader.mdf3reader` (module), 17

`mdfreader.mdf4reader` (module), 25

`mdfreader.mdfinfo3` (module), 23

`mdfreader.mdfinfo4` (module), 33

`mdfreader.mdfreader` (module), 3

`MdfSkeleton` (class in mdfreader.mdf), 11

`mdfversion` (mdfreader.mdfreader.MdfInfo attribute), 10

`MDFVersionNumber` (mdfreader.mdf.MdfSkeleton attribute), 11

`MDFVersionNumber` (mdfreader.mdf3reader.Mdf3 attribute), 18

`MDFVersionNumber` (mdfreader.mdf4reader.Mdf4 attribute), 26

`MDFVersionNumber` (mdfreader.mdfreader.Mdf attribute), 4

`merge_mdf()` (mdfreader.mdfreader.Mdf method), 7

`MLSD` (mdfreader.mdf4reader.Record attribute), 28

`multiProc` (mdfreader.mdf.MdfSkeleton attribute), 13

`multiProc` (mdfreader.mdf3reader.Mdf3 attribute), 18

`multiProc` (mdfreader.mdf4reader.Mdf4 attribute), 26

multiProc (mdfreader.mdfreader.Mdf attribute), 4

N

name (mdfreader.channel.Channel3 attribute), 41

name (mdfreader.channel.Channel4 attribute), 45

native_data_format() (mdfreader.channel.Channel4 method), 45

nBytes (mdfreader.channel.Channel3 attribute), 41

nBytes (mdfreader.channel.Channel4 attribute), 45

numberOfRecords (mdfreader.mdf3reader.Record attribute), 19

numberOfRecords (mdfreader.mdf4reader.Record attribute), 29

numpy_format() (mdfreader.channel.Channel4 method), 45

numpyDataRecordFormat (mdfreader.mdf3reader.Record attribute), 20

numpyDataRecordFormat (mdfreader.mdf4reader.Record attribute), 29

P

plot() (mdfreader.mdfreader.Mdf method), 4, 8

plot_all() (mdfreader.mdfreader.Mdf method), 8

pointer_to_data (mdfreader.mdf4reader.Data attribute), 26

pointerToData (mdfreader.mdf3reader.DATA attribute), 17

pos_bit_beg() (mdfreader.channel.Channel4 method), 45

pos_bit_end() (mdfreader.channel.Channel4 method), 46

pos_byte_beg() (mdfreader.channel.Channel4 method), 46

pos_byte_end() (mdfreader.channel.Channel4 method), 46

posByteBeg (mdfreader.channel.Channel3 attribute), 42

posByteEnd (mdfreader.channel.Channel3 attribute), 42

PythonVersion (in module mdfreader.channel), 41

PythonVersion (in module mdfreader.mdf3reader), 17

PythonVersion (in module mdfreader.mdf4reader), 25

PythonVersion (in module mdfreader.mdfinfo3), 23

PythonVersion (in module mdfreader.mdfinfo4), 33

PythonVersion (in module mdfreader.mdfreader), 3

R

read() (mdfreader.mdf3reader.DATA method), 17, 18

read() (mdfreader.mdf4reader.Data method), 26

read() (mdfreader.mdfinfo4.CABlock method), 33

read() (mdfreader.mdfinfo4.CGBlock method), 33

read() (mdfreader.mdfinfo4.DGBlock method), 36

read() (mdfreader.mdfinfo4.DLBlock method), 36

read() (mdfreader.mdfinfo4.DZBlock method), 36

read() (mdfreader.mdfinfo4.FHBlock method), 37

read() (mdfreader.mdfinfo4.HDBlock method), 37

read() (mdfreader.mdfinfo4.HLBlock method), 37

read() (mdfreader.mdfinfo4.IDBlock method), 37

read() (mdfreader.mdfreader.Mdf method), 8

read3() (mdfreader.mdf3reader.Mdf3 method), 18, 19

read4() (mdfreader.mdf4reader.Mdf4 method), 27

read_all_channels_sorted_record() (mdfreader.mdf4reader.Record method), 29

read_at_block() (mdfreader.mdfinfo4.Info4 static method), 38

read_cc() (mdfreader.mdfinfo4.CCBlock method), 33

read_cc_block() (in module mdfreader.mdfinfo3), 24

read_ce_block() (in module mdfreader.mdfinfo3), 24

read_cg_block() (in module mdfreader.mdfinfo3), 24

read_cg_block() (mdfreader.mdfinfo3.Info3 method), 23

read_cg_block() (mdfreader.mdfinfo4.Info4 method), 38

read_channels_from_bytes() (mdfreader.mdf4reader.Record method), 29

read_channels_from_bytes_fallback() (mdfreader.mdf4reader.Record method), 29

read_cm_at() (mdfreader.mdfinfo4.CommentBlock method), 34

read_cm_cc() (mdfreader.mdfinfo4.CommentBlock method), 34

read_cm_cc_unit() (mdfreader.mdfinfo4.CommentBlock method), 34

read_cm_cg() (mdfreader.mdfinfo4.CommentBlock method), 34

read_cm_ch() (mdfreader.mdfinfo4.CommentBlock method), 34

read_cm_cn() (mdfreader.mdfinfo4.CommentBlock method), 34

read_cm_cn_unit() (mdfreader.mdfinfo4.CommentBlock method), 35

read_cm_dg() (mdfreader.mdfinfo4.CommentBlock method), 35

read_cm_ev() (mdfreader.mdfinfo4.CommentBlock method), 35

read_cm_fh() (mdfreader.mdfinfo4.CommentBlock method), 35

read_cm_hd() (mdfreader.mdfinfo4.CommentBlock method), 35

read_cm_header() (mdfreader.mdfinfo4.CommentBlock method), 35

read_cm_si() (mdfreader.mdfinfo4.CommentBlock method), 35

read_cn() (mdfreader.mdfinfo4.CNBlock method), 34

read_cn_block() (in module mdfreader.mdfinfo3), 24

read_cn_block() (mdfreader.mdfinfo4.Info4 method), 38

read_composition() (mdfreader.mdfinfo4.Info4 method), 38

read_dg_block() (in module mdfreader.mdfinfo3), 24

read_dg_block() (mdfreader.mdfinfo4.Info4 method), 38

read_hd_block() (in module mdfreader.mdfinfo3), 24

read_info() (mdfreader.mdfinfo4.Info4 method), 39

read_info() (mdfreader.mdfreader.MdfInfo method), 10

read_info3() (mdfreader.mdfinfo3.Info3 method), 24

- [read_not_all_channels_sorted_record\(\)](#) (mdfreader.mdf4reader.Record method), 30
[read_record\(\)](#) (mdfreader.mdf4reader.Data method), 26
[read_record_bits\(\)](#) (mdfreader.mdf3reader.Record method), 20
[read_record_buf\(\)](#) (mdfreader.mdf3reader.Record method), 20
[read_record_buf\(\)](#) (mdfreader.mdf4reader.Record method), 30
[read_si\(\)](#) (mdfreader.mdinfo4.SIBlock method), 39
[read_sorted_record\(\)](#) (mdfreader.mdf3reader.Record method), 21
[read_sorted_record\(\)](#) (mdfreader.mdf4reader.Record method), 30
[read_sr_block\(\)](#) (mdfreader.mdinfo4.Info4 static method), 39
[read_tx\(\)](#) (mdfreader.mdinfo4.CommentBlock method), 35
[read_tx_block\(\)](#) (in module mdfreader.mdinfo3), 24
[read_xml\(\)](#) (mdfreader.mdinfo4.CommentBlock method), 36
[readRecordBits\(\)](#) (mdfreader.mdf3reader.Record method), 20
[readRecordBuf\(\)](#) (mdfreader.mdf3reader.Record method), 20
[readSortedRecord\(\)](#) (mdfreader.mdf3reader.Record method), 20
[recAttributeName](#) (mdfreader.channel.Channel3 attribute), 42
[Record](#) (class in mdfreader.mdf3reader), 19
[Record](#) (class in mdfreader.mdf4reader), 28
[record_attribute_name\(\)](#) (mdfreader.channel.Channel4 method), 46
[record_id_size\(\)](#) (mdfreader.channel.Channel4 method), 46
[RecordFormat](#) (mdfreader.channel.Channel3 attribute), 42
[recordID](#) (mdfreader.mdf3reader.Record attribute), 19
[recordID](#) (mdfreader.mdf4reader.Record attribute), 31
[recordIDCFormat](#) (mdfreader.mdf4reader.Record attribute), 31
[recordIDnumber](#) (mdfreader.mdf3reader.Record attribute), 20
[recordIDsize](#) (mdfreader.mdf4reader.Record attribute), 31
[recordLength](#) (mdfreader.mdf3reader.Record attribute), 19
[recordLength](#) (mdfreader.mdf4reader.Record attribute), 31
[recordToChannelMatching](#) (mdfreader.mdf3reader.Record attribute), 20
[recordToChannelMatching](#) (mdfreader.mdf4reader.Record attribute), 31
[remove_channel\(\)](#) (mdfreader.mdf.MdfSkeleton method), 13
[remove_channel_conversion\(\)](#) (mdfreader.mdf.MdfSkeleton method), 14
[rename_channel\(\)](#) (mdfreader.mdf.MdfSkeleton method), 14
[resample\(\)](#) (mdfreader.mdfreader.Mdf method), 4, 9
- ## S
- [set\(\)](#) (mdfreader.channel.Channel4 method), 46
[set_CANOpen\(\)](#) (mdfreader.channel.Channel4 method), 47
[set_channel_attachment\(\)](#) (mdfreader.mdf.MdfSkeleton method), 14
[set_channel_conversion\(\)](#) (mdfreader.mdf.MdfSkeleton method), 14
[set_channel_data\(\)](#) (mdfreader.mdf.MdfSkeleton method), 14
[set_channel_desc\(\)](#) (mdfreader.mdf.MdfSkeleton method), 14
[set_channel_master\(\)](#) (mdfreader.mdf.MdfSkeleton method), 14
[set_channel_master_type\(\)](#) (mdfreader.mdf.MdfSkeleton method), 14
[set_channel_unit\(\)](#) (mdfreader.mdf.MdfSkeleton method), 15
[set_invalid_bit\(\)](#) (mdfreader.mdf.MdfSkeleton method), 15
[set_invalid_bytes\(\)](#) (mdfreader.channel.Channel4 method), 47
[set_invalid_channel\(\)](#) (mdfreader.mdf.MdfSkeleton method), 15
[SIBlock](#) (class in mdfreader.mdinfo4), 39
[signal_data_type\(\)](#) (mdfreader.channel.Channel4 method), 47
[signalDataType](#) (mdfreader.channel.Channel3 attribute), 41
[SRBlock](#) (class in mdfreader.mdinfo4), 39
- ## T
- [type](#) (mdfreader.channel.Channel4 attribute), 48
[type](#) (mdfreader.mdf4reader.Data attribute), 26
- ## U
- [unique_id\(\)](#) (mdfreader.mdinfo4.Info4 method), 39
[unit](#) (mdfreader.channel.Channel3 attribute), 41
[unit\(\)](#) (mdfreader.channel.Channel4 method), 48
- ## V
- [VLSD](#) (mdfreader.mdf4reader.Record attribute), 28
[VLSD_CG](#) (mdfreader.mdf4reader.Record attribute), 28
[VLSD_CG_Flag](#) (mdfreader.channel.Channel4 attribute), 42
- ## W
- [write\(\)](#) (mdfreader.mdinfo4.CABlock method), 33

`write()` (mdfreader.mdinfo4.CGBlock method), 33
`write()` (mdfreader.mdinfo4.CNBlock method), 34
`write()` (mdfreader.mdinfo4.CommentBlock method), 36
`write()` (mdfreader.mdinfo4.DGBlock method), 36
`write()` (mdfreader.mdinfo4.DLBlock method), 36
`write()` (mdfreader.mdinfo4.DTBlock method), 36
`write()` (mdfreader.mdinfo4.DZBlock method), 36
`write()` (mdfreader.mdinfo4.FHBlock method), 37
`write()` (mdfreader.mdinfo4.HDBlock method), 37
`write()` (mdfreader.mdinfo4.HLBlock method), 37
`write()` (mdfreader.mdinfo4.IDBlock static method), 37
`write()` (mdfreader.mdfreader.Mdf method), 4, 9
`write3()` (mdfreader.mdf3reader.Mdf3 method), 19
`write4()` (mdfreader.mdf4reader.Mdf4 method), 27, 28

Z

`zipfile` (mdfreader.mdf.MdfSkeleton attribute), 15
`zipfile` (mdfreader.mdinfo4.Info4 attribute), 39
`zipfile` (mdfreader.mdfreader.MdfInfo attribute), 10